Configure Handy Macros for Confluence

- · Create a set of statuses
- Edit sets of statuses
- Remove sets of statuses
- Add statuses to a status set
- Use minimal width for Handy Status
- Edit statuses in status set
- Remove statuses from status set
- Enable or disable macros on the instance level

Configuring sets of statuses




Confluence Administrator can configure different status sets. Status sets can be configured using the "Handy Macros Settings" in the Confluence Administrator console (Confluence Administration > General Configuration > Handy Macros Settings).

Creating set of statuses

- 1. Enter the name of set.
- 2. Click Add.


Settings



Editing sets of statuses

- 1. Locate the appropriate status set.
- 2. Click Edit.
- 3. Edit the set name as you need.
- 4. Click Save.


Settings



Removing sets of statuses

- 1. Locate the appropriate status set.
- 2. Click Delete.
- 3. Confirm deletion by clicking Remove.

Settings



Configuring statuses

Adding statuses to status set

- 1. Locate and click the appropriate status set.
- 2. Enter status name.
- 3. Pick the color for text and background. There is a three ways to do so:

 - a. Select the color using the colorpicker
 b. Specify color by the text (green, black and so on)
 - c. Specify color hex code
- 4. Click Add.
- 5. Repeat steps 1-4 to add as many statuses as you need.

Settings Handy Statuses Handy Tools Settings Status Sets Statuses ø Set name Status name **Background colour** Text colour #14892c #ffffff □ • Edit Delete Status Item condition Edit Delete Events Edit Delete Changed Edit Delete


Using minimal width for status macros

This feature is available starting from Handy Macros 1.10.0.

This option allows you to make your status macros smaller when short texts for statuses are used.

- 1. Click the appropriate status set.
- 2. Click the cogwheel icon and select the **Use minimal width** option.
- 3. Click Save.

Settings



This option will be ignored if the text in the status lozenge exceeds the width of 80px.

Editing statuses in status set

- 1. Select and click the appropriate status set.
- 2. Select the appropriate status inside status set and click **Edit**.
- 3. Edit status name, text and background colors as you need.
- 4. Click Save.


Settings



Removing statuses from status set

- Locate and click the appropriate status set.
 Locate the appropriate status to delete.
- 3. Click Delete, then click Remove.

Settings



Enabling or disabling macros on the instance level

Handy Page Diff, Handy Heading and Handy Tasks can be disabled for the whole Confluence instance in the Confluence Administrator console (Confluen ce Administration > General Configuration > Handy Macros Settings).

Settings

Handy Statuses Handy Tools Settings