How to insert and remove the macros

Read more:

- How to use Table Filter maco
- How to use Chart from Table macro
- How to use Pivot Table macro
- How to use Table Transformer macro
- How to use Table from CSV macro

Inserting the macros

In the page view mode

To enable live filtration in headers:

1. Click the button on the top right corner of the page beside the Edit button.
2. Click Enable in the dialog.
3. Start filtering data in table headers

Manual entrying

1. Switch Confluence page to the edit mode.
2. Position the mouse pointer in the appropriate place on the page.
3. Start entering
    - **{Table Filter}, {Pivot Table}, {Chart from Table}, {Table Transformer}, {Table Excerpt}, {Table Excerpt Include}, {Table from CSV}** (for the legacy editor on Cloud)
    - **/Table Filter, / Pivot Table, /Chart from Table, /Table Transformer, /Table Excerpt, /Table Excerpt Include, /Table from CSV, /Table Toolbox** (for the new editor on Cloud)
4. From the prompted list of macro choices, select the macro.
5. Place the table within the macro.



Selecting in the Select macro form

1. Switch Confluence page to the edit mode.
2. Position the mouse pointer in the appropriate place on the page.
3. On the editor pane, click **Insert more content -> Other macros**.
4. In the **Select Macro** form, find the macro and insert it on the page.
5. Place the table within the macro.



Removing the macros from tables

In the page view mode (Table Filter, Pivot Table, Chart from Table)

1. Click the cogwheel icon on the filtration panel or on the pivot table or chart control panel.
2. Select the Remove the macro option.
3. Click Remove in the dialog.



Service Agent / Transaction Status	Count				
	Archived	Pending	Processed	Rejected	Total
Peter Jacobs	23	21	21	21	**86**
Christine Palmer	21	10	20	25	**76**
Ashley Stone	18	12	16	23	**69**
Tom Oliver	18	12	22	18	**70**
Andy Wilson	17	21	14	13	**65**
Gustavo Sanchez	17	19	13	21	**70**
Mark Brown	17	13	14	14	**58**
Total	**131**	**108**	**120**	**135**	**494**

In the page edit mode (all the macros)

1. Switch Confluence page to the edit mode.
2. Copy the table and paste it outside the macro body.
3. Select the macro and click Remove.