





# Getting Started


 From [version 3.0.0](#) InPlace Editor for Confluence supports editing headings placed within layout sections and macros.

1. Once InPlace Editor for Confluence has been installed, you will see the Pencil icons next to the headings on Confluence Pages.


Pages / [Vadim Rutkevich's Home](#)

 [Edit](#)  [Watch](#)  [Share](#)  [Tools](#) ▾

## CIPE Add-on - Description


 Added by Vadim Rutkevich, last modified by Vadim Rutkevich on Dec 05, 2013 [\(view change\)](#)

General Information



Add-on name	InPlace Editor for Confluence
Add-on tagline	Edit long pages as individual sections in the pop-up form with the native Confluence editor and rich capabilities.
More details	<p>InPlace Editor for Confluence delivers a convenient way to instantly edit large pages by parts enclosed within section headings.</p> <p>This add-on provides you with the following capabilities:</p> <ul style="list-style-type: none"><li>• Quick edit of page sections in the pop-up form with standard Confluence editor.</li><li>• Easy selection of spaces where the section editing can be used and where it remains disabled.</li><li>• Temporary deactivation of the edit-by-parts functionality from the user interface when needed</li></ul>

2. If you click the Pencil icon for some heading, the visual editor opens in the pop-up form. Here you can make the required modifications in text, add images and tables, use macros and work as if using the native Confluence Editor.



3. You can temporarily disable the add-on right from the Tools menu.

Pages / Vadim Rutkevich's Home

## CIPE Add-on - Description

Added by Vadim Rutkevich, last edited by Vadim Rutkevich on Dec 05, 2013 (view change)

### General Information

<b>Add-on name</b>	InPlace Editor for Confluence
<b>Add-on tagline</b>	Edit long pages as individual sections in the pop-up form with the native Confluence editor and rich capabilities.
<b>More details</b>	<p>InPlace Editor for Confluence delivers a convenient way to instantly edit large pages by parts enclosed within section headings.</p> <p>This add-on provides you with the following capabilities:</p> <ul style="list-style-type: none"> <li>• Quick edit of page sections in the pop-up form with standard Confluence editor.</li> <li>• Easy selection of spaces where the section editing can be used and where it remains disabled.</li> <li>• Temporary deactivation of the edit-by-parts functionality from the user interface when needed.</li> </ul>

- Attachments (8)
- Page History
- Restrictions
- Favourite
- Disable InPlace Editor**
- Page Information
- Link to this Page...
- View in Hierarchy
- View Source
- Export to PDF
- Export to Word
- Import Word Document
- Copy
- Move
- Delete

4. Your Confluence Administrator can quickly configure the add-on. The add-on can be activated only for appropriate spaces or for specific heading levels. Additionally, the add-on can be automatically enabled on newly created spaces. You can also select a suitable mode for editing headings. Use the Single Heading mode (known as the Show only selected headings before InPlace Editor 3.0.5), which allows you to exclude the adjacent heading levels for showing in InPlace editor form, when you start editing the heading of the higher level. You can also choose the click area to open the editor between the pencil icon only and the whole heading.

# InPlace Editor Settings

General configuration

License

InPlace Editor Settings

Edit

- ☒ Enabling InPlace Editor on new spaces
- If you want to enable the plugin on new spaces manually you should disable this option

Enable InPlace Editor for: **H1 H2 H3 H4**

- Heading Edit Mode
- ☒ Combined Headings

Edit the page section enclosed between heading levels of the same level specified in the configuration or to the nearest heading of the higher level
- ☐ Single Heading

Edit only the page section with one of the heading levels specified in the configuration

- Open InPlace Editor by clicking:
- ☒ The heading or the pencil icon

Click the heading or the pencil icon to open the editor
- ☐ Only the pencil icon

Click the pencil icon to open the editor

Edit

Edit

## Enable InPlace Editor by space

Name	Key
Alexander Kuznetsov	~alexkuznetsov
Alexander Ovsyannikov	~aovsyannikov
Andrey Khaneev	~akhaneev
Awesome Graphs for Bitbucket Cloud	AGBB
Awesome Graphs for Bitbucket Server	AWEGRAPHS

 The main difference between InPlace Editor 3.0.5+ and older versions is the following:

InPlace Editor 3.0.5+ opens sections with the selected heading levels, and also includes adjacent sections to the next section with the heading of the same level.

#### How the Show only selected headings option works

This option may be either enabled or disabled so behavior of InPlace editor will differ on the page of the following structure:

- H1 + text1
- H2 + text2
- H4 + text4
- H5 + text5
- H1 + text1A
- H5 + text5A

Option is disabled	Option is enabled
<p>InPlace Editor is enabled for H1, H2 and H4 heading levels.</p> <p>When you click the Pencil icon for H1 + text1, you will get InPlace Editor form with the H1 + text1 paragraph. When you click the Pencil icon for H1 + text1A, you will get InPlace Editor form with the H1 + text1A and H5 + text5A. The adjacent headings of the lower levels will be included into the editor form with the heading of the higher level standing above. The same behavior will be if you click H4 + text4, you will get H4 + text4 and H5 + text5 paragraphs in the editor form.</p>	<p>InPlace Editor is enabled for H1, H2 and H4 heading levels.</p> <p>When you click the Pencil icon for H1 + text1, you will get InPlace Editor form with the H1 + text1 paragraph. When you click the Pencil icon for H1 + text1A, you will get InPlace Editor form with the H1 + text1A only. H5 + text5A paragraph will not be included. The adjacent headings of the lower levels are not included into the editor form when you open the heading of the higher level standing above. The same behavior will be if you click H4 + text4, you will get H4 + text4 only. H5 + text5 and H5 + text5A paragraphs can be edited only in standard Confluence editor while editing the whole page.</p>

#### How the Heading Edit Mode works

Since InPlace Editor 3.0.5 the **Show only selected headings** option was renamed to "Single Heading" edit mode with the same behaviour. Default

Behavior of the InPlace Editor was modified for loading more contents on pages with multi-level headings.

You can configure combined headings mode or single heading mode for the InPlace Editor. Behaviour of the add-on will differ on the page with the following structure:

- H1 + text1
- H2 + text2
- H4 + text4
- H5 + text5
- H1 + text1A
- H5 + text5A

Combined Headings mode	Single Heading mode
<p>InPlace Editor is enabled for H1, H2 and H4 heading levels.</p> <p>When you click the Pencil icon for H1 + text1, you will get InPlace Editor form with the H1 + text1 to the H5 + text5 paragraphs. When you click the Pencil icon for H1 + text1A, you will get InPlace Editor form with the H1 + text1A and H5 + text5A. The adjacent headings of the lower levels will be included into the editor form with the heading of the higher level standing above. The same behavior will be if you click H4 + text4, you will get H4 + text4 and H5 + text5 paragraphs in the editor form.</p>	<p>InPlace Editor is enabled for H1, H2 and H4 heading levels.</p> <p>When you click the Pencil icon for H1 + text1, you will get InPlace Editor form with the H1 + text1 paragraph. When you click the Pencil icon for H1 + text1A, you will get InPlace Editor form with the H1 + text1A only. H5 + text5A paragraph will not be included. The adjacent headings of the lower levels are not included into the editor form when you open the heading of the higher level standing above. The same behavior will be if you click H4 + text4, you will get H4 + text4 only. H5 + text5 and H5 + text5A paragraphs can be edited only in standard Confluence editor while editing the whole page.</p>

**5. The space administrator can override the global configuration set by Confluence administrator. In the Space Tools, the space administrator should select Add-ons and on the InPlace Editor tab set the appropriate configuration for the space.**

# Space Tools

[Overview](#) [Permissions](#) [Content Tools](#) [Look and Feel](#) [Integrations](#) [Scroll Office](#) **Add-ons**

## InPlace Editor

Enable InPlace Editor for:

H1  
H2  
H3  
H4

Heading Edit Mode

☒ Combined Headings

Edit the page section enclosed between heading levels of the same level specified in the configuration or to the nearest heading of the higher level

☐ Single Heading

Edit only the page section with one of the heading levels specified in the configuration

Open InPlace Editor by clicking:

☐ The heading or the pencil icon

Click the heading or the pencil icon to open the editor

☒ Only the pencil icon

Click the pencil icon to open the editor

Edit



The space administrator can reset the space specific configuration to the global configuration by clicking the **Reset to default** button.